

Media Platform Solutions | AS-20502

Novaspread-S Reference manual

Version:

0.16

Date issued:

29 May 2015

STRICTLY CONFIDENTIAL



Important Notice

This document has been produced by SES Platform Services GmbH (SES PS). Certain product names or brand names may be trademarks or designations of their respective owners.

Liability/Copyright

© Copyright by SES Platform Services, 2015

SES Platform Services GmbH

Beta Straße 1-10

D-85774 Unterföhring

Germany

This document is protected by copyright, all rights reserved. It may not be duplicated or published, either whole, in part, or in a modified version, without explicit written permission by SES Platform Services GmbH.

Cooperation

This document has been developed in cooperation with:

TARA Systems GmbH

Gmunder Str. 53

81379 München

Germany





TABLE OF CONTENT

1.	Introduction	6
1.1.	Purpose of document	6
1.2.	Document history	€
1.3.	References	
2.	Provided API	7
2.1.	Novaspread Basic Types	7
2.2.	NovaspreadServer	
2.2.1.	NovaspreadTServerInitParameter	8
2.2.2.	NovaspreadServerInit	
2.2.3.	NovaspreadServerDone	
2.2.4.	NovaspreadServerProcess	
2.2.5.	NovaspreadServerFactoryReset	
2.2.6.	NovaspreadServerSetFriendlyName	9
2.2.7.	NovaspreadServerGetDeviceList	10
2.2.8.	NovaspreadServerSelectDevice	10
2.2.9.	NovaspreadServerGetSelectedDevice	
2.2.10.	NovaspreadServerCreateSatIpTuner	11
2.3.	NovaspreadDeviceList	11
2.3.1.	NovaspreadDeviceListRelease	
2.3.2.	NovaspreadDeviceListGetLength	
2.3.3.	NovaspreadDeviceListGetDevice	
2.4.	NovaspreadDevice	12
2.4.1.	NovaspreadDeviceRelease	
2.4.2.	NovaspreadDeviceGetlpAddress	
2.4.3.	NovaspreadDeviceGetFriendlyName	
2.4.4.	NovaspreadDeviceGetManufacturer	
2.4.5. 2.4.6.	NovaspreadDeviceGetManufacturerUrl NovaspreadDeviceGetModelDescription	
2.4.0.	NovaspreadDeviceGetModelNumber	
2.4.7.	NovaspreadDeviceGetModelUrl	
2.4.9.	NovaspreadDeviceGetNouelOn	
2.4.10.		
2.5.	NovaspreadlconList	
2.5.1.	NovaspreadlconListRelease	
2.5.2.	NovaspreadlconListGetLength	
2.5.3.	NovaspreadlconListGetlcon	16
2.6.	Novaspreadicon	17
2.6.1.	NovaspreadlconRelease	
2.6.2.	NovaspreadlconGetMimeType	
2.6.3.	NovaspreadlconGetWidth	
2.6.4.	NovaspreadlconGetHeight	
2.6.5.	NovaspreadlconGetDepth	18
2.6.6.	NovaspreadlconGetUrl	
2.7.	NovaspreadTunerParameters	40
2.7.1.	NovaspreadTunerType	
2.7.1.	NovaspreadTTunerCodeRate	
2.7.2.	NovaspreadTTunerModulationSystem	
2.7.3. 2.7.4.	NovaspreadTTunerModulation	
2.7.5.	NovaspreadTTunerParamDvbS	
2.7.6.	NovaspreadTTunerParamValue	



2.7.7.	NovaspreadTTunerParameters	22
2.7.8.	NovaspreadTTunerSignalInfo	22
0.0	Management dTransport discuss	00
2.8.	NovaspreadTranscoding	
2.8.1.	NOVASPREAD_PID_UNKNOWN	
2.8.2.	NovaspreadTVideoCodec	
2.8.3.	NovaspreadTVideoResolution	
2.8.4.	NovaspreadTAudioCodec	
2.8.5.	NovaspreadTTranscodingInput	
2.8.6.	NovaspreadTTranscodingOutput	
2.8.7.	NovaspreadTTranscoding	
2.8.8.	NovaspreadTVideoTranscodingCapability	
2.8.9.	NovaspreadTAudioTranscodingCapability	21
2.9.	NovaspreadSatlpTuner	27
2.9.1.	NovaspreadTSatIpTunerConnectionStatus	
2.9.2.	NovaspreadTSatIpTunerConnectionStatusChangeListener	
2.9.3.	NovaspreadTSatIpTunerDataAvailableListener	
2.9.4.	NovaspreadSatIpTunerDestroy	
2.9.5.	NovaspreadSatIpTunerSetParameters	20
2.9.6.	NovaspreadSatIpTunerGetParameters	
2.9.7.	NovaspreadSatIpTunerConnect	
2.9.8.	NovaspreadSatIpTunerDisconnect	
2.9.9.	NovaspreadSatIpTunerGetConnectionStatus	
2.9.10.	NovaspreadSatIpTunerSetConnectionStatusChangeListener	
2.9.10.		
2.9.11.	NovaspreadSatIpTunerSetPids	
2.9.12.	NovaspreadSatIpTunerGetPids	
	NovaspreadSatIpTunerAddPids	
2.9.14.		
2.9.16.		
2.9.17.		
2.9.18.	NovaspreadSatIpTunerReadData	35
2.10.	NovaspreadCaInfo	35
2.10.1.	NovaspreadTCaInfoSmartcardStatus	
2.10.1.	NovaspreadCaInfoCreate	
2.10.2.	NovaspreadCaInfoDestroy	
2.10.3.		
2.10.4.	NovaspreadCaInfoSetChipsetType	
2.10.6.	NovaspreadCaInfoSetChipsetRevision	
2.10.7.		
2.10.7.		
	NovaspreadCainioSetCaVersion NovaspreadCainfoSetCaNumber	
	NovaspreadCalnioSetCandinber	
	. NovaspreadCalnioSetSmartcardSuitable	
	. NovaspreadCalnioSetSmartcardType	
	NovaspreadCaInfoSetSmartcardNumber	
	. NovaspreadCaInfoSetSmartcardStatus	
2.10.15.	. NovaspreadCaInfoSetExpirationDate	41
3.	Required API	42
3.1.	NovaspreadHost	42
3.1.1.	NovaspreadTHostCapabilities	
3.1.2.	NovaspreadHostGetCapabilities	
3.1.3.	NovaspreadHostAllocateTuner	
3.1.4.	NovaspreadHostReleaseTuner	
0.0	Management	
3.2.	NovaspreadTuner	
3.2.1.	NovaspreadTTunerError	
3.2.2.	NovaspreadTTunerState	
3.2.3.	NovaspreadTTunerStateChangeListener	
3.2.4.	NovaspreadTTunerDataAvailableListener	46



J.Z.J.	Novaspread i runeraliocation Parameter	40
3.2.6.	NovaspreadTTunerAllocationFinishedListener	47
3.2.7.	NovaspreadTTunerReleaseRequestedListener	47
3.2.8.	NovaspreadTunerGetTransportSessionId	47
3.2.9.	NovaspreadTunerSetTranscoding	48
3.2.10.	NovaspreadTunerSetStateChangeListener	48
3.2.11.	NovaspreadTunerGetError	49
3.2.12.	NovaspreadTunerSetPids	49
3.2.13.	NovaspreadTunerAddPids	
3.2.14.	NovaspreadTunerRemovePids	50
3.2.15.	NovaspreadTunerStart	
3.2.16.	NovaspreadTunerStop	51
3.2.17.	NovaspreadTunerlsLocked	
3.2.18.	NovaspreadTunerGetSignalInfo	
3.2.19.	NovaspreadTunerSetDataAvailableListener	52
3.2.20.	NovaspreadTunerReadData	53
3.3.	NovaspreadCa	
3.3.1.	NovaspreadTCaDvbId	
3.3.2.	NovaspreadTCaPlatformUsageRulesReceivedListener	
3.3.3.	NovaspreadTCaServiceUsageRulesReceivedListener	
3.3.4.	NovaspreadCaGetInfo	
3.3.5.	NovaspreadCaSetDvbId	
3.3.6.	NovaspreadCaSetPlatformUsageRulesReceivedListener	
3.3.7.	NovaspreadCaSetServiceUsageRulesReceivedListener	56
3.4.	NovaspreadDrm	57
3.4. 3.4.1.	NovaspreadTDrmLicense	31
·		
3.4.2. 3.4.3.	NovaspreadTDrmLicenseParameter	
3.4.3. 3 <i>4 4</i>	NovaspreadDrmStop	58 58
	NOV2CDTQ20LITM>TOD	- AX



1. INTRODUCTION

1.1. Purpose of document

This document describes the required and provided interfaces of Novaspread-S in the scope of the Multiscreen product of SES Platform Services.

1.2. Document history

Version	Date	Author	Changes	
0.16	2015-05-29	Manfred Schmidt	Working draft	
		Georg Kamjunke		

1.3. References


[1] SPS; "AS-20001: Multiscreen"[2] SPS; "AS-20501: Novaspread-S"



2. PROVIDED API

The following section describes the Application Programming Interface (API) which is provided by Novaspread-S. To use the interface in an application include the NovaspreadServer.h.

The following diagram gives an overview of the classes provided by Novaspread-S.



2.1. Novaspread Basic Types

Novaspread uses the following basic types:

NovaspreadTInt16 - A 8-bit signed integer
NovaspreadTInt16 - A 16-bit signed integer
NovaspreadTInt32 - A 32-bit signed integer
NovaspreadTUInt8 - A 8-bit unsigned integer
NovaspreadTUInt16 - A 16-bit unsigned integer
NovaspreadTUInt32 - A 32-bit unsigned integer

NovaspreadTBoolean - A boolean type which can have the values NOVASPREAD_TRUE or NOVASPREAD_FALSE

NOVASPREAD_NULL - A null-reference

2.2. NovaspreadServer

A NovaspreadServer represents the Novaspread-S main class. Before the NovaspreadServer can be used it must be initialised with the function NovaspreadServerInit(). With the function NovaspreadServerDone() the NovaspreadServer is shutdown again.

With the function NovaspreadServerSetFriendlyName() the name of the SAT>IP server provided by the NovaspreadServer is defined.

To access other (standard) SAT>IP servers a device list of all SAT>IP servers can be retrieved with the function NovaspreadServerGetDeviceList(). One of these SAT>IP servers is selected with the function



NovaspreadServerSelectDevice(). SAT>IP tuners are only accessed from the selected SAT>IP server. A SAT>IP tuner can be allocated with the function NovaspreadServerCreateSatIpTuner() and used by the host device to receive parts of a transport streams.

2.2.1. NovaspreadTServerInitParameter

This type defines initialization parameters for NovaspreadServer. It is recommended to initialize this struct with all 0 (see example below).

SYNTAX

```
typedef struct
{
   const char * DataPath;
} NovaspreadTServerInitParameter;
```

COMPONENTS

DataPath

Path to a directory within the local file system, were NovaspreadServer can store its configuration data.

EXAMPLE

```
NovaspreadTServerInitParameter initParameters;

memset( &initParameters, 0, sizeof( initParameters ));
initParameters.DataPath = "/data";
NovaspreadServerInit( &initParameters );
```

2.2.2. NovaspreadServerInit

This function initializes the NovaspreadServer. It must be called once, before any other NovaspreadServer function is called.

SYNTAX

```
PUBLIC NovaspreadTBoolean
NovaspreadServerInit(
   NovaspreadTServerInitParameter * aInitParameter );
```

PARAMETERS

aInitParameter

The initialization parameter for NovaspreadServer.

RETURN VALUE

```
NOVAS PREAD_TRUE
if successful.

NOVAS PREAD_FALSE
otherwise.
```

SEE ALSO

```
NovaspreadTServerInitParameter NovaspreadServerDone()
```

2.2.3. NovaspreadServerDone

This function shuts down the NovaspreadServer. After this function is called no other functions of the NovaspreadServer shall be called.



SYNTAX

```
PUBLIC void
NovaspreadServerDone(
   void );
```

SEE ALSO

NovaspreadServerInit()

2.2.4. NovaspreadServerProcess

This function must be called periodically to process the NovaspreadServer.

SYNTAX

```
PUBLIC NovaspreadTBoolean
NovaspreadServerProcess(
   void );
```

RETURN VALUE

```
NOVASPREAD_TRUE
if there is still something to process and this function should be called again.

NOVASPREAD_FALSE
if nothing is available to process.
```

2.2.5. NovaspreadServerFactoryReset

Resets the NovaspradServer to factory defaults.

SYNTAX

```
PUBLIC NovaspreadTBoolean
NovaspreadServerFactoryReset(
```

RETURN VALUE

```
NOVAS PREAD_TRUE
if successful.

NOVAS PREAD_FALSE
otherwise.
```

2.2.6. NovaspreadServerSetFriendlyName

Sets the friendly name used by the SAT>IP Server. If the friendly name is changed by calling this function the SAT>IP UPnP device is restarted to advertise the new name in the UPnP device description. Ongoing streamings may be stopped.

SYNTAX

```
PUBLIC NovaspreadTBoolean
NovaspreadServerSetFriendlyName(
   const char * aFriendlyName);
```

PARAMETERS

```
aFriendlyName
```

The friendly name as UTF-8 encoded string.

RETURN VALUE

```
NOVASPREAD_TRUE if successful.
```



NOVASPREAD_FALSE otherwise.

2.2.7. NovaspreadServerGetDeviceList

Gets the currently available list of SAT>IP Servers. The DeviceList contains all (standard) SAT>IP server devices which have been detected in the local network at the moment when the function is called. The returned list is a copy and does not change, if e.g. a new SAT>IP server was found after getting the list. To get an updated list, the list must be released and retrieved again with this function. The SAT>IP Server provided by the NovaspreadServer is excluded from this list to avoid self-referencing.

When the DeviceList is no longer used, the function NovaspreadDeviceListRelease() must be called to release it.

SYNTAX

```
PUBLIC NovaspreadTDeviceList
NovaspreadServerGetDeviceList(
  void );
```

RETURN VALUE

A new DeviceList. NOVASPREAD_NULL if an error occurred.

SEE ALSO

```
NovaspreadTDeviceList
NovaspreadDeviceListRelease()
```

2.2.8. NovaspreadServerSelectDevice

With this function a SAT>IP server device is selected. SatlpTuners will only be used from this selected device.

If a call to this function changes the selected device, all currently connected SatlpTuners will be disconnected. If NOVASPREAD_NULL is passed as Device, SatlpTuners can no longer connect to a SAT>IP server.

SYNTAX

```
PUBLIC NovaspreadTBoolean

NovaspreadServerSelectDevice(
NovaspreadTDevice aDevice);
```

PARAMETERS

aDevice

The SAT>IP server device to be selected.

RETURN VALUE

```
NOVAS PREAD_TRUE
if successful.

NOVAS PREAD_FALSE
otherwise.
```

SEE ALSO

```
NovaspreadServerGetDeviceList()
NovaspreadServerCreateSatIpTuner()
```

2.2.9. NovaspreadServerGetSelectedDevice

Gets the currently selected SAT>IP server device.

SYNTAX

```
PUBLIC NovaspreadTDevice
NovaspreadServerGetSelectedDevice(
```



void);

RETURN VALUE

The selected device. NOVASPREAD_NULL if no device has been selected.

SEE ALSO

NovaspreadServerSelectDevice()

2.2.10. NovaspreadServerCreateSatlpTuner

Creates a new SatlpTuner. A SatlpTuner can be used to receive transport stream data from a SAT>IP server, that is available in the local network. If the SatlpTuner is no longer used, call NovaspreadSatlpTunerRelease() to free it. The function call is non-blocking, i.e. it returns immediately. To actually allocate a SatlpTuner from the selected SAT>IP server device call the function NovaspreadSatlpTunerConnect().

SYNTAX

```
PUBLIC NovaspreadTSatIpTuner
NovaspreadServerCreateSatIpTuner(
   void );
```

RETURN VALUE

A new SatlpTuner. NOVASPREAD_NULL if an error occurred.

SEE ALSO

```
NovaspreadTSatIpTuner
NovaspreadSatIpTunerConnect()
```

2.3. NovaspreadDeviceList

A DeviceList holds Devices which have been found via UPnP device detection in the network. Call NovaspreadServerGetDeviceList() to get a list of detected Devices. A DeviceList represents a snapshot of the Devices when the list is retrieved. The DeviceList is not changed afterwards even if new Devices are found or disappeared from the network. To update a list for the user interface simply retrieve the list again to get a current snapshot of this list.

2.3.1. NovaspreadDeviceListRelease

Releases this DeviceList. After calling this function the list shall no longer be accessed. Each DeviceList returned by the function NovaspreadServerGetDeviceList() must be released with this function when it is no longer used.

SYNTAX

```
PUBLIC void
NovaspreadDeviceListRelease(
  NovaspreadTDeviceList This );
```

PARAMETERS

This

The DeviceList.

SEE ALSO

NovaspreadServerGetDeviceList()

2.3.2. NovaspreadDeviceListGetLength

Gets the number of Devices stored in this list. If the list is empty 0 is returned.



SYNTAX

```
PUBLIC NovaspreadTUInt32
NovaspreadDeviceListGetLength(
   NovaspreadTDeviceList This);
```

PARAMETERS

This

The DeviceList.

RETURN VALUE

The number of Devices stored in this list.

2.3.3. NovaspreadDeviceListGetDevice

Gets the Device at the given index from the DeviceList. The returned Device must be released by calling NovaspreadDeviceRelease(), when it is no longer needed. The first Device in the list has the index 0.

SYNTAX

```
PUBLIC NovaspreadTDevice

NovaspreadDeviceListGetDevice(

NovaspreadTDeviceList This,

NovaspreadTUInt32 aIndex);
```

PARAMETERS

This

The DeviceList.

aIndex

The index of the Device to be returned.

RETURN VALUE

A Device. NOVASPREAD_NULL if the given index is invalid.

SEE ALSO

```
NovaspreadTDevice
NovaspreadDeviceListGetLength()
```

2.4. NovaspreadDevice

A Device represents a SAT>IP server which was found via UPnP in the local network. The Device provides information that are retrieved from the UPnP device description provided by the SAT>IP server.

The list of Devices can be retrieved with the function NovaspreadServerGetDeviceList(). To get access to the properties of a Device, use the function NovaspreadDeviceListGetDevice().

2.4.1. NovaspreadDeviceRelease

Release this Device. This function must be called for each Device retrieved with the functions NovaspreadDeviceListGetDevice() when the Device is no longer used.

SYNTAX

```
PUBLIC void

NovaspreadDeviceRelease(
NovaspreadTDevice This);
```

PARAMETERS

This



The Device.

SEE ALSO

NovaspreadDeviceListGetDevice()

2.4.2. NovaspreadDeviceGetlpAddress

Gets the IP address of this Device.

SYNTAX

```
PUBLIC const char *
NovaspreadDeviceGetIpAddress(
   NovaspreadTDevice This);
```

PARAMETERS

This

The Device.

RETURN VALUE

The IP address as UTF-8 encoded string. NOVASPREAD_NULL is returned if not defined or if an error occurred.

2.4.3. NovaspreadDeviceGetFriendlyName

Gets the friendly name of this Device.

SYNTAX

```
PUBLIC const char *
NovaspreadDeviceGetFriendlyName(
   NovaspreadTDevice This);
```

PARAMETERS

This

The Device.

RETURN VALUE

The friendly name as UTF-8 encoded string. NOVASPREAD_NULL is returned if not defined or if an error occurred.

2.4.4. NovaspreadDeviceGetManufacturer

Gets the manufacturer information of this Device.

SYNTAX

```
PUBLIC const char *
NovaspreadDeviceGetManufacturer(
  NovaspreadTDevice This);
```

PARAMETERS

This

The Device.

RETURN VALUE

The manufacturer as UTF-8 encoded string. NOVASPREAD_NULL is returned if not defined or if an error occurred.



2.4.5. NovaspreadDeviceGetManufacturerUrl

Gets the manufacturer's URL.

SYNTAX

```
PUBLIC const char *
NovaspreadDeviceGetManufacturerUrl(
   NovaspreadTDevice This);
```

PARAMETERS

This

The Device.

RETURN VALUE

The manufacturer's URL as UTF-8 encoded string. NOVASPREAD_NULL is returned if not defined or if an error occurred.

2.4.6. NovaspreadDeviceGetModelDescription

Gets the model description.

SYNTAX

```
PUBLIC const char *
NovaspreadDeviceGetModelDescription(
   NovaspreadTDevice This);
```

PARAMETERS

This

The Device.

RETURN VALUE

The model description as UTF-8 encoded string. NOVASPREAD_NULL is returned if not defined or if an error occurred.

2.4.7. NovaspreadDeviceGetModelNumber

Gets the model number.

SYNTAX

```
PUBLIC const char *
NovaspreadDeviceGetModelNumber(
   NovaspreadTDevice This);
```

PARAMETERS

This

The Device

RETURN VALUE

The model number as UTF-8 encoded string. NOVASPREAD_NULL is returned if not defined or if an error occurred.

2.4.8. NovaspreadDeviceGetModelUrl

Gets the model's URL.



SYNTAX

```
PUBLIC const char *
NovaspreadDeviceGetModelUrl(
   NovaspreadTDevice This);
```

PARAMETERS

This

The Device.

RETURN VALUE

The model URL as UTF-8 encoded string. NOVASPREAD_NULL is returned if not defined or if an error occurred.

2.4.9. NovaspreadDeviceGetSerialNumber

Gets the serial number.

SYNTAX

```
PUBLIC const char *
NovaspreadDeviceGetSerialNumber(
   NovaspreadTDevice This);
```

PARAMETERS

This

The Device.

RETURN VALUE

The serial number as UTF-8 encoded string. NOVASPREAD_NULL is returned if not defined or if an error occurred

2.4.10. NovaspreadDeviceGetIconList

Gets the IconList defined for this Device. The returned IconList must be released with the function NovaspreadIconListRelease() if it is no longer used.

SYNTAX

```
PUBLIC NovaspreadTIconList
NovaspreadDeviceGetIconList(
   NovaspreadTDevice This);
```

PARAMETERS

This

The Device.

RETURN VALUE

The IconList. NOVASPREAD_NULL if an error occurred.

SEE ALSO

```
NovaspreadTIconList
NovaspreadIconListRelease()
```

2.5. NovaspreadlconList

For each Device a list of Icons can be retrieved. An Icon is used for a graphical user interface. The IconList class represents a list of Icons.



2.5.1. NovaspreadlconListRelease

Releases this IconList. After calling this function the list shall no longer be accessed. Each time an IconList is retrieved with the function NovaspreadDeviceGetIconList() this function must be called to release the IconList.

SYNTAX

```
PUBLIC void
NovaspreadIconListRelease(
    NovaspreadTIconList This);
PARAMETERS
This
```

SEE ALSO

NovaspreadDeviceGetIconList()

2.5.2. NovaspreadlconListGetLength

Gets the number of Icons stored in this list. If the IconList is empty this function returns 0.

SYNTAX

```
PUBLIC NovaspreadTUInt32
NovaspreadIconListGetLength(
  NovaspreadTIconList This);
```

PARAMETERS

This

The IconList

The IconList

RETURN VALUE

The number of Icons stored in this list. 0 if the IconList is empty.

SEE ALSO

NovaspreadIconListGetIcon()

2.5.3. NovaspreadlconListGetlcon

Gets the Icon at the given index from the IconList. The returned Icon must be released by calling NovaspreadIconRelease(), when it is no longer needed. The index starts with 0 for the first icon in the IconList.

SYNTAX

```
PUBLIC NovaspreadTicon

NovaspreadIconListGetIcon(

NovaspreadTiconList This,

NovaspreadTUInt32 aIndex);
```

PARAMETERS

This

The IconList

aIndex

The index of the Icon to be returned.

RETURN VALUE

The Icon at the given index position. NOVASPREAD_NULL if the given index is invalid.



2.6. Novaspreadlcon

Defines an Icon used for a Device. Properties of an Icon are the width, height and color depth and the URL from where the icon image file can be loaded.

2.6.1. NovaspreadIconRelease

Releases the Icon. After calling this function, the Icon shall no longer be accessed. Each Icon that is retrieved with the function NovaspreadIconListGetIcon() must be released with this function.

SYNTAX

```
PUBLIC void
NovaspreadIconRelease(
NovaspreadTIcon This);

PARAMETERS

This
The Icon.
```

SEE ALSO

NovaspreadIconListGetIcon()

2.6.2. NovaspreadIconGetMimeType

Gets the MIME type of the Icon. The MIME type is a null-terminated ASCII string that defines the format of the Icon, e.g. "image/png", "image/jpeg".

SYNTAX

```
PUBLIC const char *
NovaspreadIconGetMimeType(
   NovaspreadTIcon This);
```

PARAMETERS

This
The Icon.

RETURN VALUE

The MIME type as null-terminated ASCII string.

2.6.3. NovaspreadlconGetWidth

Gets the width of the Icon in pixels.

SYNTAX

```
PUBLIC NovaspreadTUInt16
NovaspreadIconGetWidth(
   NovaspreadTIcon This);
```

PARAMETERS

This

The Icon.

RETURN VALUE

The width of the Icon.



SEE ALSO

NovaspreadIconGetHeight()

2.6.4. NovaspreadlconGetHeight

Gets the height of the Icon in pixels.

SYNTAX

```
PUBLIC NovaspreadTUInt16
NovaspreadIconGetHeight(
   NovaspreadTIcon This );
```

PARAMETERS

This

The Icon.

RETURN VALUE

The height of the Icon.

SEE ALSO

NovaspreadIconGetWidth()

2.6.5. NovaspreadlconGetDepth

Gets the color depth of the Icon. The returned value indicates the number of colors of the Icon.

SYNTAX

```
PUBLIC NovaspreadTUInt32
NovaspreadIconGetDepth(
   NovaspreadTIcon This);
```

PARAMETERS

This

The Icon.

RETURN VALUE

The color depth of the Icon.

2.6.6. NovaspreadlconGetUrl

Gets the URL of the Icon. From this URL the Icon can be downloaded.

SYNTAX

```
PUBLIC const char *
NovaspreadIconGetUrl(
  NovaspreadTIcon This);
```

PARAMETERS

This

The Icon.

RETURN VALUE

The URL as UTF-8 encoded string.

2.7. NovaspreadTunerParameters



TunerParameters define the types for tuning parameters.

2.7.1. NovaspreadTTunerType

NovaspreadTunerType defines the different types of tuners. Which tuners are actually supported depends on the target platform. Currently only DVB-S tuners are supported.

SYNTAX

```
typedef enum
{
    NOVASPREAD_TUNER_TYPE_DVB_S
```

} NovaspreadTTunerType;

COMPONENTS

```
NOVASPREAD_TUNER_TYPE_DVB_S
A DVB-S tuner receives data from a satellite
```

2.7.2. NovaspreadTTunerCodeRate

This type defines the code rates.

SYNTAX

```
typedef enum
{

NOVASPREAD_TUNER_CODE_RATE_UNKNOWN,

NOVASPREAD_TUNER_CODE_RATE_AUTO,

NOVASPREAD_TUNER_CODE_RATE_1_2,

NOVASPREAD_TUNER_CODE_RATE_1_3,

NOVASPREAD_TUNER_CODE_RATE_1_4,

NOVASPREAD_TUNER_CODE_RATE_2_3,

NOVASPREAD_TUNER_CODE_RATE_2_5,

NOVASPREAD_TUNER_CODE_RATE_2_5,

NOVASPREAD_TUNER_CODE_RATE_3_4,

NOVASPREAD_TUNER_CODE_RATE_3_5,

NOVASPREAD_TUNER_CODE_RATE_4_5,

NOVASPREAD_TUNER_CODE_RATE_4_5,

NOVASPREAD_TUNER_CODE_RATE_5_6,

NOVASPREAD_TUNER_CODE_RATE_5_6,

NOVASPREAD_TUNER_CODE_RATE_5_7,

NOVASPREAD_T
```

} NovaspreadTTunerCodeRate;

Represents a code rate of 2/5

COMPONENTS

```
NOVASPREAD_TUNER_CODE_RATE_UNKNOWN
The code rate is unknown. This value shall not be used for setting the tuner parameters.

NOVASPREAD_TUNER_CODE_RATE_AUTO
If this code rate is used, the tuner tries to find out the correct code rate automatically.

NOVASPREAD_TUNER_CODE_RATE_1_2
Represents a code rate of 1/2

NOVASPREAD_TUNER_CODE_RATE_1_3
Represents a code rate of 1/3

NOVASPREAD_TUNER_CODE_RATE_1_4
Represents a code rate of 1/4

NOVASPREAD_TUNER_CODE_RATE_2_3
Represents a code rate of 2/3

NOVASPREAD_TUNER_CODE_RATE_2_3
Represents a code rate of 2/3
```



```
NOVASPREAD TUNER CODE RATE 3 4
  Represents a code rate of 3/4
NOVASPREAD_TUNER_CODE_RATE_3_5
  Represents a code rate of 3/5
NOVASPREAD TUNER CODE RATE 4 5
 Represents a code rate of 4/5
NOVASPREAD TUNER CODE_RATE_5_6
  Represents a code rate of 5/6
NOVASPREAD_TUNER_CODE_RATE_6_7
 Represents a code rate of 6/7
NOVASPREAD TUNER CODE RATE 7 8
 Represents a code rate of 7/8
NOVASPREAD TUNER CODE RATE 8 9
  Represents a code rate of 8/9
NOVASPREAD TUNER CODE RATE 9 10
  Represents a code rate of 9/10
NOVASPREAD TUNER CODE RATE LAST
 The last code rate parameter. For internal use only.
```

SEE ALSO

NovaspreadTTunerParameters

2.7.3. NovaspreadTTunerModulationSystem

This type represents the supported modulation systems which are necessary for DVB-S2 tuners.

SYNTAX

```
typedef enum
{
  NOVASPREAD_TUNER_MODULATION_SYSTEM_DVB_S,
  NOVASPREAD_TUNER_MODULATION_SYSTEM_DVB_S2
} NovaspreadTunerModulationSystem;
```

COMPONENTS

```
NOVASPREAD_TUNER_MODULATION_SYSTEM_DVB_S
The modulation system 'DVB-S'.

NOVASPREAD_TUNER_MODULATION_SYSTEM_DVB_S2
The modulation system 'DVB-S2'.
```

2.7.4. NovaspreadTTunerModulation

This enumeration type defines the supported modulation types for DVB tuners. For each tuner type (e.g. DVB-S) only a selection of the listed modulation types can be used.

SYNTAX

```
typedef enum {
    NOVASPREAD_TUNER_MODULATION_UNKNOWN,
    NOVASPREAD_TUNER_MODULATION_AUTO,
    NOVASPREAD_TUNER_MODULATION_OPSK,
    NOVASPREAD_TUNER_MODULATION_QAM_16,
    NOVASPREAD_TUNER_MODULATION_QAM_32,
    NOVASPREAD_TUNER_MODULATION_QAM_64,
    NOVASPREAD_TUNER_MODULATION_QAM_64,
    NOVASPREAD_TUNER_MODULATION_QAM_128,
```



```
NOVASPREAD_TUNER_MODULATION_QAM_256, NOVASPREAD_TUNER_MODULATION_LAST
```

} NovaspreadTTunerModulation;

COMPONENTS

```
NOVASPREAD TUNER MODULATION UNKNOWN
```

The modulation is unknown. This value shall not be used for setting the tuner parameters.

```
NOVASPREAD TUNER MODULATION AUTO
```

If this modulation is used, the tuner tries to find out the correct modulation automatically.

```
NOVASPREAD_TUNER_MODULATION_QPSK
```

Represents a QPSK modulation.

NOVASPREAD_TUNER_MODULATION_8PSK

Represents a 8PSK modulation.

NOVASPREAD_TUNER_MODULATION_QAM_16

Represents a 16-QAM modulation.

NOVASPREAD TUNER MODULATION QAM 32

Represents a 32-QAM modulation.

NOVASPREAD_TUNER_MODULATION_QAM_64

Represents a 64-QAM modulation.

NOVASPREAD_TUNER_MODULATION_QAM_128

Represents a 128-QAM modulation.

NOVASPREAD TUNER MODULATION QAM 256

Represents a 256-QAM modulation.

NOVASPREAD TUNER MODULATION LAST

The last modulation parameter. For internal use only.

2.7.5. NovaspreadTTunerParamDvbS

This structure contains the tuning parameters a DVB-S tuner.

SYNTAX

} NovaspreadTTunerParamDvbS;

COMPONENTS

SourceId

This sourceld is passed to the SAT>IP server. Set to 0 if not used.

OrbitalPosition

In 1/10 degrees. e.g. Astra 19.2E = 192

Frequency

The transponder frequency in KHz to tune to.

SymbolRate

Kilo-symbols per second.

CodeRate

The code rate of the transponder.



ModulationSystem

The used modulation system. This is only necessary for DVB-S2 tuner. DVB-S tuner will ignore it.

Modulation

The modulation of the transponder.

2.7.6. NovaspreadTTunerParamValue

This union contains the parameters for the different types of tuners. Currently only DVB-S/S2 is supported.

SYNTAX

```
typedef union
{
  NovaspreadTTunerParamDvbS DvbS;
} NovaspreadTTunerParamValue;
```

COMPONENTS

DvbS

The tuning parameters specific for DVB-S/S2 reception.

2.7.7. NovaspreadTTunerParameters

This data structure defines the tuning parameters to be set at a tuner. It defines the type of tuner (currently only DVB-S) for which the parameters are to be set. Depending on this type the Value is interpreted.

SYNTAX

COMPONENTS

Туре

The type of the tuner.

Value

Structure containing the tuning parameters specific for a type of tuner.

SEE ALSO

```
NovaspreadHostAllocateTuner()
```

2.7.8. NovaspreadTTunerSignalInfo

This type defines the SignalInfo of a tuner. The SignalInfo contains the Level and the Quality of the signal received by the Tuner. For a specification of the SignalInfo see SAT>IP Protocol Specification V1.2.2.

SYNTAX

```
typedef struct
{
  NovaspreadTUInt8 Level;
  NovaspreadTUInt8 Quality;
}
NovaspreadTTunerSignalInfo;
```

COMPONENTS

Level



Numerical value between 0 and 255. An incoming L-band satellite signal of -25dBm corresponds to 224, -65dBm corresponds to 32 and no signal corresponds to 0.

```
Quality
```

Numerical value between 0 and 15. Lower values indicate to higher error rates. The value 15 indicates a BER lower than 2.0E-4 after Viterbi for DVB-S, a BER lower than 10.0E-7 for DVB-S2.

SEE ALSO

```
NovaspreadTunerGetSignalInfo()
NovaspreadSatIpTunerGetSignalInfo()
```

2.8. NovaspreadTranscoding

NovaspreadTranscoding defines all types which are used for transcoding. Transcoding is controlled with the Tuner by the function NovaspreadTunerSetTranscoding(). The NovaspreadTTranscoding structure defined in this section contains all necessary parameters.

2.8.1. NOVASPREAD_PID_UNKNOWN

This constant defines the value to be used for an unknown PID. It is used e.g. in NovaspreadTTranscodingInput, if no audio stream resp. video stream shall be transcoded.

SYNTAX

```
#define NOVASPREAD_PID_UNKNOWN 0xFFFF
```

SEE ALSO

NovaspreadTTranscodingInput

2.8.2. NovaspreadTVideoCodec

This enumeration type defines all available video codecs used for transcoding. The video codec is used for the TranscodingInput parameters to indicate the used video codec of the input video stream. It is also used for the TranscodingOutput parameters to indicate the video codec to be output by the Transcoder. The list of supported video codecs depends on the platform.

SYNTAX

```
typedef enum
{
    NOVASPREAD_VIDEO_CODEC_MPEG_2,
    NOVASPREAD_VIDEO_CODEC_AVC,
    NOVASPREAD_VIDEO_CODEC_HEVC,
    NOVASPREAD_VIDEO_CODEC_LAST
```

} NovaspreadTVideoCodec;

COMPONENTS

```
NOVASPREAD_VIDEO_CODEC_MPEG_2
MPEG-2 video

NOVASPREAD_VIDEO_CODEC_AVC
H.264 video (MPEG-4 AVC). The following profile shall be used: HP@L4.

NOVASPREAD_VIDEO_CODEC_HEVC
High Efficiency Video Coding (HEVC). The following profile shall be used: MP@L4.1 Main Tier.

NOVASPREAD_VIDEO_CODEC_LAST
For internal use only.
```

SEE ALSO

NovaspreadTTranscodingInput



NovaspreadTTranscodingOutput

2.8.3. NovaspreadTVideoResolution

This enumeration type defines the possible video resolutions to be used by the Transcoder for the video output. The supported video resolutions depend on the platform.

SYNTAX

```
typedef enum
      NOVASPREAD_VIDEO_RESOLUTION_176_144P, NOVASPREAD_VIDEO_RESOLUTION_352_288P,
      NOVASPREAD VIDEO RESOLUTION 720 576P,
      NOVASPREAD_VIDEO_RESOLUTION_720_5761,
NOVASPREAD_VIDEO_RESOLUTION_1280_720P,
      NOVASPREAD_VIDEO_RESOLUTION_1920_1080P,
      NOVASPREAD VIDEO RESOLUTION 1920 10801,
      NOVASPREAD VIDEO RESOLUTION LAST
    } NovaspreadTVideoResolution;
COMPONENTS
    NOVASPREAD VIDEO RESOLUTION 176 144P
       176x144 progressive
    NOVASPREAD VIDEO RESOLUTION 352 288P
      352x288 progressive
    NOVASPREAD VIDEO RESOLUTION 720 576P
      720x576 progressive
    NOVASPREAD VIDEO RESOLUTION 720 5761
      720x576 interlaced
    NOVASPREAD VIDEO RESOLUTION 1280 720P
       1280x720 progressive
    NOVASPREAD VIDEO RESOLUTION 1920 1080P
       1920x1080 progressive
    NOVASPREAD VIDEO RESOLUTION 1920 10801
       1920x1080 interlaced
```

SEE ALSO

NovaspreadTTranscodingOutput

NOVASPREAD VIDEO RESOLUTION LAST

2.8.4. NovaspreadTAudioCodec

For internal use only

This enumeration type defines the different audio codecs used for transcoding. The audio codec is used for the TranscodingInput parameters to indicate the used audio codec of the input audio stream. It is also used for the TranscodingOutput parameters to indicate the audio codec to be output by the Transcoder. The list of supported audio codecs depends on the platform.

SYNTAX

```
typedef enum
{

NOVASPREAD_AUDIO_CODEC_MP2,
NOVASPREAD_AUDIO_CODEC_AC3,
NOVASPREAD_AUDIO_CODEC_AAC,
NOVASPREAD_AUDIO_CODEC_HE_AAC,
NOVASPREAD_AUDIO_CODEC_LAST
```

} NovaspreadTAudioCodec;



COMPONENTS

```
NOVASPREAD_AUDIO_CODEC_MP2
MPEG-1 Audio Layer II

NOVASPREAD_AUDIO_CODEC_AC3
Dolby Digital

NOVASPREAD_AUDIO_CODEC_AAC
Advanced Audio Coding (AAC)

NOVASPREAD_AUDIO_CODEC_HE_AAC
High-Efficiency Advanced Audio Coding (HE-AAC). The following profile shall be used: HE-AAC v1.

NOVASPREAD_AUDIO_CODEC_LAST
For internal use only
```

SEE ALSO

NovaspreadTTranscodingInput NovaspreadTTranscodingOutput

2.8.5. NovaspreadTTranscodingInput

This TranscodingInput type defines the parameters of the input stream to be transcoding. The PIDs for audio, video and PCR as well as the audio and video codecs of the input stream are defined.

SYNTAX

} NovaspreadTTranscodingInput;

COMPONENTS

AudioPid

The pid of the audio stream. If set to NOVASPREAD_PID_UNKNOWN, no audio stream shall be transcoded.

AudioCodec

The codec of the stream.

VideoPid

The pid of the video stream. If set to NOVASPREAD_PID_UNKNOWN, no video stream shall be transcoded.

VideoCodec

The codec of the stream.

PcrPid

The pid containing the PCR information.

SEE ALSO

NovaspreadTTranscoding

2.8.6. NovaspreadTTranscodingOutput

The TranscodingOuput type defines the output properties of the transcoded stream.

SYNTAX

```
typedef struct
{
```



NovaspreadTAudioCodec AudioCodec; NovaspreadTUInt32 AudioBitrate; NovaspreadTVideoCodec VideoCodec; NovaspreadTVideoResolution VideoResolution; NovaspreadTUInt32 VideoBitrate;

} NovaspreadTTranscodingOutput;

COMPONENTS

AudioCodec

The AudioCodec of the transcoded audio stream. See NovaspreadTAudioCodec for a list of possible values.

AudioBitrate

The bit rate of the transcoded audio stream in kbits/sec.

VideoCodec

The VideoCodec of the transcoded video stream. See NovaspreadTVideoCodec for a list of possible values.

VideoResolution

The resolution of the transcoded video stream.

VideoBitrate

The maximum bit rate of the transcoded video stream in kbits/sec.

SEE ALSO

```
NovaspreadTAudioCodec
NovaspreadTVideoCodec
NovaspreadTTranscoding
```

2.8.7. NovaspreadTTranscoding

This type defines all transcoding parameters for the input and output audio and video streams.

SYNTAX

```
typedef struct
{
  NovaspreadTTranscodingInput Input;
  NovaspreadTTranscodingOutput Output;
```

} NovaspreadTTranscoding;

COMPONENTS

Input

The input parameters of the stream to transcode.

Output

The output parameters of the transcoded stream.

SEE ALSO

```
NovaspreadTTranscodingInput
NovaspreadTTranscodingOutput
NovaspreadTHostCapabilities
NovaspreadTunerSetTranscoding()
```

2.8.8. NovaspreadTVideoTranscodingCapability

VideoTranscodingCapability describes the capability of a video transcoder for transcoding to a particular VideoCodec.

SYNTAX

```
typedef struct
```



} NovaspreadTVideoTranscodingCapability;

COMPONENTS

```
VideoCodec
```

The destination VideoCodec.

MinBitrate

The minimal bit rate in Kilobits/sec.

MaxBitrate

The maximal bit rate in Kilobits/sec.

2.8.9. NovaspreadTAudioTranscodingCapability

AudioTranscodingCapability describes the capability of an audio transcoder for transcoding to a particular AudioCodec.

SYNTAX

```
typedef struct
{
  NovaspreadTAudioCodec AudioCodec;
  NovaspreadTUInt32 MinBitrate;
  NovaspreadTUInt32 MaxBitrate;
```

} NovaspreadTAudioTranscodingCapability;

COMPONENTS

AudioCodec

The destination AudioCodec.

MinBitrate

The minimal bit rate in Kilobits/sec.

MaxBitrate

The maximal bit rate in Kilobits/sec.

2.9. NovaspreadSatlpTuner

A SatIpTuner can be used to receive transport stream data from a SAT>IP server which is available in the local network.

To create SatIpTuner call the function NovaspreadSeverCreateSatIpTuner(). Only SatIpTuners from the selected SAT>IP server device are used.

After creation a SatlpTuner is not connected to a SAT>IP server. To connect to a SAT>IP server, tuner parameters must be set at the SatlpTuner with the function NovaspreadSatlpTunerSetParameters() and then NovaspreadSatlpTunerConnect() must be called. By calling NovaspreadSatlpTunerSetPids(), the pids that shall be received from the SAT>IP server are defined.

As soon as the SatlpTuner has changed its ConnectionStatus to CONNECTED, NovaspreadSatlpTunerReadData() will provide transport stream data.

2.9.1. NovaspreadTSatlpTunerConnectionStatus

A SatIpTuner is in one of the following ConnectionStatus.



SYNTAX

```
typedef enum
{
   NOVASPREAD_SAT_IP_TUNER_CONNECTION_STATUS_NOT_CONNECTED,
   NOVASPREAD_SAT_IP_TUNER_CONNECTION_STATUS_CONNECTING,
   NOVASPREAD_SAT_IP_TUNER_CONNECTION_STATUS_CONNECTED
```

} NovaspreadTSatIpTunerConnectionStatus;

COMPONENTS

```
NOVASPREAD SAT IP TUNER CONNECTION STATUS NOT CONNECTED
```

After creating a SatlpTuner, the tuner is in ConnectionStatus NOT_CONNECTED. It is not connected to any SAT>IP server. This ConnectionStatus is also reached, when NovaspreadSatlpTunerDisconnect() is called, resp. from CONNECTING, when it was not possible to establish a connection.

```
NOVASPREAD SAT IP TUNER CONNECTION STATUS CONNECTING
```

When NovaspreadSatlpTunerConnect() was called successfully, the SatlpTuner is in ConnectionStatus CONNECTING.

```
NOVASPREAD SAT IP TUNER CONNECTION STATUS CONNECTED
```

When a SatIpTuner connected successfully to a SAT>IP server, it changed to ConnectionStatus CONNECTED. Transport stream data can be read from the tuner by calling NovaspreadSatIpTunerReadData().

SEE ALSO

```
NovaspreadSatIpTunerConnect()
NovaspreadSatIpTunerDisconnect()
NovaspreadSatIpTunerGetConnectionStatus()
```

2.9.2. NovaspreadTSatlpTunerConnectionStatusChangeListener

A function of this type can be set at a SatlpTuner. It is called every time the ConnectionStatus of the SatlpTuner changes.

SYNTAX

PARAMETERS

aContext

This context is passed unchanged from NovaspreadSatlpTunerSetConnectionStatusChangeListener().

```
aSatIpTuner
```

The status of this tuner has changed.

```
aNewStatus
```

The new status.

SEE ALSO

```
{\tt NovaspreadSatIpTunerSetConnectionStatusChangeListener()}
```

2.9.3. NovaspreadTSatlpTunerDataAvailableListener

A function of this type can be set at the SatlpTuner. When NovaspreadSatlpTunerReadData() returns 0, because no data is available, the registered DataAvailableListener will be called as soon as data is available again.

SYNTAX

```
typedef void
(* NovaspreadTSatIpTunerDataAvailableListener ) (
```



```
void * aContext );
```

PARAMETERS

aContext

This context is passed unchanged from the NovaspreadSatlpTunerSetDataAvailableListener() function.

SEE ALSO

```
NovaspreadSatIpTunerSetDataAvailableListener()
NovaspreadSatIpTunerReadData()
```

2.9.4. NovaspreadSatlpTunerDestroy

Destroys the given SatlpTuner. The SatlpTuner may not be accessed after calling this function.

SYNTAX

```
PUBLIC void
NovaspreadSatIpTunerDestroy(
   NovaspreadTSatIpTuner This );
```

PARAMETERS

This

The SatlpTuner.

2.9.5. NovaspreadSatIpTunerSetParameters

Sets the tuning parameters of this SatlpTuner. Tuning parameters define the transponder from where the transport stream is to be received.

SYNTAX

```
PUBLIC NovaspreadTBoolean

NovaspreadSatIpTunerSetParameters(

NovaspreadTSatIpTuner This,

NovaspreadTTunerParameters * aParameter);
```

PARAMETERS

This

The SatlpTuner.

aParameter

The TunerParameters. See data type NovaspreadTTunerParameters for a description of all tuning parameters.

RETURN VALUE

```
NOVASPREAD_TRUE
if the parameters were set successfully.

NOVASPREAD_FALSE
if an error occurred.
```

SEE ALSO

```
\label{local_normalization} No vaspread \texttt{SatIpTunerGetParameters} \ ()
```

2.9.6. NovaspreadSatlpTunerGetParameters

Gets the currently set TunerParameters.



SYNTAX

```
PUBLIC NovaspreadTBoolean

NovaspreadSatIpTunerGetParameters (
NovaspreadTSatIpTuner This,
NovaspreadTTunerParameters * aParameter );
```

PARAMETERS

This

The SatlpTuner.

aParameter

OUT: Pointer to variable of type NovaspreadTTunerParameters, where the function returns the currently set TunerParameters.

RETURN VALUE

```
NOVASPREAD_TRUE
if the TunerParameters are returned successfully.

NOVASPREAD_FALSE
```

if an error occurred. In this case the variable aParameters points to is not unchanged.

SEE ALSO

```
NovaspreadTTunerParameters
NovaspreadSatIpTunerSetParameters()
```

2.9.7. NovaspreadSatlpTunerConnect

This function is called to establish a connection of the SatlpTuner with a SAT>IP server in the network. During this call the SatlpTuner changes its ConnectionStatus to CONNECTING.

As soon as the connection is established successfully, the ConnectionStatus is changed to CONNECTED. From this point in time received transport stream packets can be retrieved with the function NovaspreadSatlpTunerReadData().

SYNTAX

```
PUBLIC NovaspreadTBoolean
NovaspreadSatIpTunerConnect(
  NovaspreadTSatIpTuner This );
```

PARAMETERS

This

The SatlpTuner.

RETURN VALUE

```
NOVASPREAD_TRUE
if the tuner started connecting successfully.

NOVASPREAD_FALSE
otherwise.
```

SEE ALSO

```
NovaspreadTSatIpTunerConnectionStatus NovaspreadSatIpTunerDisconnect()
```

2.9.8. NovaspreadSatlpTunerDisconnect

Disconnects a SatlpTuner from a SAT>IP server.

SYNTAX

PUBLIC void



```
NovaspreadSatIpTunerDisconnect(
  NovaspreadTSatIpTuner This);
```

PARAMETERS

This

The SatlpTuner.

SEE ALSO

NovaspreadTSatIpTunerConnectionStatus NovaspreadSatIpTunerConnect()

2.9.9. NovaspreadSatlpTunerGetConnectionStatus

Gets the ConnectionStatus of a SatlpTuner.

SYNTAX

```
PUBLIC NovaspreadTSatIpTunerConnectionStatus
NovaspreadSatIpTunerGetConnectionStatus(
   NovaspreadTSatIpTuner This);
```

PARAMETERS

This

The SatlpTuner.

RETURN VALUE

The current ConnectionStatus of the SatlpTuner.

SEE ALSO

```
NovaspreadTSatIpTunerConnectionStatus NovaspreadSatIpTunerConnect()
```

2.9.10. NovaspreadSatlpTunerSetConnectionStatusChangeListener

This function sets a ConnectionStatusChangeListener at a SatlpTuner.

SYNTAX

PARAMETERS

```
This
```

The SatlpTuner

aListener

The listener to be set. PASS NOVASPREAD_NULL to unset the listener.

aContext

This context is passed unchanged to the listener.

RETURN VALUE

```
NOVAS PREAD_TRUE
if successful

NOVAS PREAD_FALSE
otherwise
```



SEE ALSO

 ${\tt NovaspreadTSatIpTunerConnectionStatusChangeListener}$

2.9.11. NovaspreadSatlpTunerSetPids

Sets the pids which shall be available in the stream received by this Tuner. This function overwrites the pids previously enabled for the SatlpTuner. To reset all pids, pass aPids=NOVASPREAD_NULL and aNoOfPids=0.

SYNTAX

```
PUBLIC NovaspreadTBoolean

NovaspreadSatIpTunerSetPids (

NovaspreadTSatIpTuner This,

NovaspreadTUInt16 * aPids,

NovaspreadTUInt32 aNoOfPids );

PARAMETERS

This
The SatIpTuner.

aPids
The array of pids.

aNoOfPids
The number of pids in the array.
```

RETURN VALUE

```
NOVASPREAD_TRUE
if successful

NOVASPREAD_FALSE
otherwise
```

SEE ALSO

NovaspreadSatIpTunerGetPids()

2.9.12. NovaspreadSatlpTunerGetPids

Gets the pids that are currently enabled for streaming.

SYNTAX

```
PUBLIC NovaspreadTBoolean

NovaspreadSatIpTunerGetPids (

NovaspreadTSatIpTuner This,
NovaspreadTUInt16 * aPids,
NovaspreadTUInt32 aMaxNoOfPids,
NovaspreadTUInt32 * aNoOfPids );

PARAMETERS

This
The SatIpTuner.
```

The Sauprune

OUT: Pointer to an array of UInt16 where the function stores the currently enabled pids

aMaxNoOfPids

The maximal number of pids that can be copied into the aPids array.

aNoOfPids

OUT: The number of pids that are copied into the aPids array.



RETURN VALUE

```
NOVASPREAD TRUE
   if successful
NOVASPREAD FALSE
    otherwise
```

SEE ALSO

NovaspreadSatIpTunerSetPids()

2.9.13. NovaspreadSatlpTunerAddPids

Adds pids, which shall additionally be received by this Tuner.

SYNTAX

```
PUBLIC NovaspreadTBoolean
NovaspreadSatIpTunerAddPids(
  NovaspreadTSatIpTuner This,
  NovaspreadTUInt16 * aPids,
NovaspreadTUInt32 aNoOfF
                          aNoOfPids );
  NovaspreadTUInt32
```

PARAMETERS

```
This
 The SatlpTuner.
```

The array of pids that shall additionally be received.

aNoOfPids

The number of pids in the array.

RETURN VALUE

```
NOVASPREAD TRUE
   if successful.
NOVASPREAD FALSE
    otherwise.
```

2.9.14. NovaspreadSatlpTunerRemovePids

Removes pids, which should no longer be received by this Tuner.

SYNTAX

```
PUBLIC void
NovaspreadSatIpTunerRemovePids (
  NovaspreadTSatIpTuner This,
  NovaspreadTUInt16 * NovaspreadTUInt32
                           aPids,
                           aNoOfPids );
```

PARAMETERS

```
This
  The SatlpTuner.
  The array of pids that should no longer be streamed.
  The number of pids in the array.
```

2.9.15. NovaspreadSatlpTunerlsLocked

AS-20502 33



Returns the lock status of the tuner. A Tuner is locked if a signal is detected for the set TunerParameter and the demodulator is able to decode the signal. A Tuner receives data only if it is locked.

SYNTAX

```
PUBLIC NovaspreadTBoolean
NovaspreadSatIpTunerIsLocked(
NovaspreadTSatIpTuner This);

PARAMETERS

This
The SatIpTuner.

RETURN VALUE

NOVASPREAD_TRUE
if the SatIpTuner is locked.
```

NOVASPREAD_FALSE otherwise.

2.9.16. NovaspreadSatlpTunerGetSignalInfo

Gets the current SignalInfo of the SatIpTuner. See data type NovaspreadTTunerSignalInfo for a description of the returned data.

SYNTAX

```
PUBLIC NovaspreadTTunerSignalInfo
NovaspreadSatIpTunerGetSignalInfo(
   NovaspreadTSatIpTuner This);
```

PARAMETERS

This

The SatlpTuner.

RETURN VALUE

The current SignalInfo.

SEE ALSO

NovaspreadTTunerSignalInfo

2.9.17. NovaspreadSatlpTunerSetDataAvailableListener

Sets a DataAvailableListener. Only one DataAvailableListener can be set at a SatlpTuner.

SYNTAX

```
PUBLIC NovaspreadTBoolean

NovaspreadSatIpTunerSetDataAvailableListener(

NovaspreadTSatIpTuner This,

NovaspreadTSatIpTunerDataAvailableListener aListener,

void * aContext);

PARAMETERS

This
The SatIpTuner.

aListener
The DataAvailableListener. Pass NOVASPREAD_NULL to unset the listener.
```

aContext
This context is passed unchanged to the listener.



RETURN VALUE

```
NOVAS PREAD_TRUE
if successful.

NOVAS PREAD_FALSE
otherwise.
```

SEE ALSO

```
NovaspreadTSatIpTunerDataAvailableListener NovaspreadSatIpTunerReadData()
```

2.9.18. NovaspreadSatlpTunerReadData

As soon as the SatlpTuner is in ConnectionStatus CONNECTED, this function will write 188 bytes long transport stream packets to the buffer. This function must be called periodically to avoid a SatlpTuner internal buffer overflow.

If this function is called when the SatlpTuner is in a different ConnectionStatus, it will not write data to the buffer and return 0.

If NovaspreadSatlpTunerReadData() is called in ConnectionStatus CONNECTED and no data is available, 0 will be returned. As soon as data is available again, a previously set DataAvailableListener will be called. Do not call NovaspreadSatlpTunerReadData() in the context of the DataAvailableListener.

SYNTAX

```
PUBLIC NovaspreadTUInt32

NovaspreadSatIpTunerReadData(

NovaspreadTSatIpTuner This,

NovaspreadTUInt8 * aBuffer,

NovaspreadTUInt32 aBufferSize);
```

PARAMETERS

```
This
The SatlpTuner.

aBuffer
Transport stream packets are written to this buffer.

aBufferSize
The size of the buffer. Any buffer size is allowed.
```

RETURN VALUE

The number of bytes written to the buffer. If there are no transport stream packets available 0 is returned.

2.10. NovaspreadCaInfo

A NovaspreadCaInfo represent all information that is returned via a "GET /rc/ca" request as defined in "FreeTV Remote Control Specification v1.0" and "FREETVA-RC Profile AS-30102 HD+ Platform v1.0".

2.10.1. NovaspreadTCaInfoSmartcardStatus

This type defines various smartcard status.

SYNTAX

```
typedef enum
{
    NOVASPREAD_CA_INFO_SMARTCARD_STATUS_ACTIVATING,
    NOVASPREAD_CA_INFO_SMARTCARD_STATUS_NOT_ACTIVATED,
    NOVASPREAD_CA_INFO_SMARTCARD_STATUS_ACTIVATED,
```



```
NOVASPREAD_CA_INFO_SMARTCARD_STATUS_TUNE, NOVASPREAD_CA_INFO_SMARTCARD_STATUS_EXPIRED
```

} NovaspreadTCaInfoSmartcardStatus;

COMPONENTS

```
NOVASPREAD_CA_INFO_SMARTCARD_STATUS_ACTIVATING
The smartcard is currently activating.

NOVASPREAD_CA_INFO_SMARTCARD_STATUS_NOT_ACTIVATED
The smartcard is not yet activated.

NOVASPREAD_CA_INFO_SMARTCARD_STATUS_ACTIVATED
The smartcard is activated.

NOVASPREAD_CA_INFO_SMARTCARD_STATUS_TUNE
Tune to a specific channel.

NOVASPREAD_CA_INFO_SMARTCARD_STATUS_EXPIRED
The smartcard is expired.
```

2.10.2. NovaspreadCaInfoCreate

Creates a new Calnfo.

SYNTAX

```
PUBLIC NovaspreadTCaInfo
NovaspreadCaInfoCreate(
   void );
```

RETURN VALUE

A new Calnfo if successful. NOVASPREAD_NULL otherwise.

SEE ALSO

NovaspreadCaInfoDestroy()

2.10.3. NovaspreadCaInfoDestroy

Destroys the given Calnfo.

SYNTAX

```
PUBLIC void
NovaspreadCaInfoDestroy(
  NovaspreadTCaInfo This );
```

PARAMETERS

This

This Calnfo.

SEE ALSO

NovaspreadCaInfoCreate()

2.10.4. NovaspreadCaInfoSetChipsetUid

Sets the chipset unique ID.

SYNTAX

```
PUBLIC NovaspreadTBoolean
NovaspreadCaInfoSetChipsetUid(
  NovaspreadTCaInfo This,
  const char * aChipsetUid);
```



37

PARAMETERS

```
This Calnfo.

aChipsetUid
The chipset unique ID.
```

RETURN VALUE

```
NOVASPREAD_TRUE
if successful.

NOVASPREAD_FALSE
otherwise.
```

2.10.5. NovaspreadCaInfoSetChipsetType

Sets the chipset type.

SYNTAX

```
PUBLIC NovaspreadTBoolean
NovaspreadCaInfoSetChipsetType(
  NovaspreadTCaInfo This,
  const char * aChipsetType);
```

PARAMETERS

This Calnfo.

aChipsetType
The type of the chipset.

RETURN VALUE

```
NOVAS PREAD_TRUE
if successful.

NOVAS PREAD_FALSE
otherwise.
```

2.10.6. NovaspreadCaInfoSetChipsetRevision

Sets the chipset revision.

SYNTAX

```
PUBLIC NovaspreadTBoolean
NovaspreadCaInfoSetChipsetRevision(
  NovaspreadTCaInfo This,
  const char * aChipsetRevision);
```

PARAMETERS

```
This Calnfo

aChipsetRevision
The chipset revision.
```

RETURN VALUE

```
NOVASPREAD_TRUE
if successful.
NOVASPREAD_FALSE
```

AS-20502



otherwise.

2.10.7. NovaspreadCaInfoSetCaVendor

Sets the CAS vendor.

SYNTAX

```
PUBLIC NovaspreadTBoolean
NovaspreadCaInfoSetCaVendor(
  NovaspreadTCaInfo This,
  const char * aCaVendor);
```

PARAMETERS

This

This Calnfo.

aCaVendor

The CAS vendor.

RETURN VALUE

```
NOVAS PREAD_TRUE
if successful.

NOVAS PREAD_FALSE
otherwise.
```

2.10.8. NovaspreadCaInfoSetCaVersion

Sets the CAS version.

SYNTAX

```
PUBLIC NovaspreadTBoolean
NovaspreadCaInfoSetCaVersion(
  NovaspreadTCaInfo This,
  const char * aCaVersion);
```

PARAMETERS

This Calnfo.

aCaVersion

The CAs version.

RETURN VALUE

```
NOVASPREAD_TRUE
if successful.

NOVASPREAD_FALSE
otherwise.
```

2.10.9. NovaspreadCaInfoSetCaNumber

Sets the CAS serial number.

SYNTAX

```
PUBLIC NovaspreadTBoolean
NovaspreadCaInfoSetCaNumber(
  NovaspreadTCaInfo This,
  const char * aCaNumber);
```



PARAMETERS

```
This Calnfo.

aCaNumber
The CAS serial number.
```

RETURN VALUE

```
NOVAS PREAD_TRUE
if successful.

NOVAS PREAD_FALSE
otherwise.
```

2.10.10. NovaspreadCaInfoSetSmartcardInserted

Sets whether a smartcard is inserted or not.

SYNTAX

```
PUBLIC NovaspreadTBoolean
NovaspreadCaInfoSetSmartcardInserted(
   NovaspreadTCaInfo This,
   NovaspreadTBoolean aInserted);
```

PARAMETERS

This

This Calnfo.

aInserted

NOVASPREAD_TRUE if a smartcard is inserted. NOVASPREAD_FALSE otherwise.

RETURN VALUE

```
NOVAS PREAD_TRUE
if successful.

NOVAS PREAD_FALSE
otherwise.
```

2.10.11. NovaspreadCaInfoSetSmartcardSuitable

Sets if the smartcard is suitable for the Operator.

SYNTAX

```
PUBLIC NovaspreadTBoolean

NovaspreadCaInfoSetSmartcardSuitable(
NovaspreadTCaInfo This,
NovaspreadTBoolean aSuitable);
```

PARAMETERS

```
This
```

This Calnfo.

aSuitable

NOVASPREAD_TRUE if the inserted smartcard is suitable. NOVASPREAD_FALSE otherwise.

RETURN VALUE

```
NOVASPREAD_TRUE
if successful.

NOVASPREAD FALSE
```



otherwise.

2.10.12. NovaspreadCaInfoSetSmartcardType

Sets the type and/or version of the smartcard.

SYNTAX

```
PUBLIC NovaspreadTBoolean

NovaspreadCaInfoSetSmartcardType(
  NovaspreadTCaInfo This,
  const char * aType);

AMETERS
```

PARAMETERS

This Calnfo.

aType

The type and/or version.

RETURN VALUE

```
NOVAS PREAD_TRUE
if successful.

NOVAS PREAD_FALSE
otherwise.
```

2.10.13. NovaspreadCaInfoSetSmartcardNumber

Sets the smartcard's serial number.

SYNTAX

```
PUBLIC NovaspreadTBoolean
NovaspreadCaInfoSetSmartcardNumber(
  NovaspreadTCaInfo This,
  const char * aNumber);
```

PARAMETERS

```
This Calnfo.
```

aNumber

The serial number.

RETURN VALUE

```
NOVASPREAD_TRUE
if successful.

NOVASPREAD_FALSE
otherwise.
```

2.10.14. NovaspreadCaInfoSetSmartcardStatus

Sets the smartcard status information as defined by the operator.

SYNTAX

```
PUBLIC NovaspreadTBoolean

NovaspreadCaInfoSetSmartcardStatus(

NovaspreadTCaInfo This,

NovaspreadTCaInfoSmartcardStatus aStatus);
```



PARAMETERS

```
This Calnfo.

aStatus
The status.
```

RETURN VALUE

```
NOVAS PREAD_TRUE
if successful.

NOVAS PREAD_FALSE
otherwise.
```

SEE ALSO

NovaspreadTCaInfoSmartcardStatus

2.10.15. NovaspreadCaInfoSetExpirationDate

Sets the expiration date. The expiration date shall be set if the status of the smartcard is ACTIVATED.

SYNTAX

```
PUBLIC NovaspreadTBoolean
NovaspreadCaInfoSetExpirationDate(
  NovaspreadTCaInfo This,
  NovaspreadTUInt32 aDate);
```

PARAMETERS

```
This
The Calnfo
```

The expiration date in UTC (seconds since 1 Jan 1970).

RETURN VALUE

```
NOVAS PREAD_TRUE
if successful.

NOVAS PREAD_FALSE
otherwise.
```




3. REQUIRED API

The following section describes the Application Programming Interface (API) which is required by Novaspread-S. All functions described in this section must be implemented for the target platform to which Novaspread-S is ported.

To use the interface include the file NovaspreadHost.h.

The following diagram gives an overview of the classes required by Novaspread-S.



3.1. NovaspreadHost

The Host is a required interface used by the NovaspreadServer. All methods must be implemented on target platforms to which NovaspreadServer is ported.

3.1.1. NovaspreadTHostCapabilities

The HostCapabilities describe the capabilities of the tuners, transcoders and transcryptors. The capabilities can be retrieved from the Host by calling NovaspreadHostGetCapabilities().

SYNTAX

} NovaspreadTHostCapabilities;



COMPONENTS

```
NoOfTuners
```

The total number of tuners that are managed by the Host.

NoOfTranscoders

The total number of transcoders. This shall be set to 0, if transcoding is not supported at all.

NoOfTranscryptors

The total number of transcryptors. This shall be set to 0, if transcryption is not supported at all.

NoOfVideoTranscodingCapabilities

The number of TranscodingCapabilities returned in VideoTranscodingCapabilities.

VideoTranscodingCapabilities[NOVASPREAD_VIDEO_CODEC_LAST]
A list of supported VideoTranscodings.

NoOfAudioTranscodingCapabilities

The number of TranscodingCapabilities returned in AudioTranscodingCapabilities.

AudioTranscodingCapabilities[NOVASPREAD_AUDIO_CODEC_LAST]
A list of supported AudioTranscodings.

SEE ALSO

```
NovaspreadTVideoTranscodingCapability
NovaspreadTAudioTranscodingCapability
```

3.1.2. NovaspreadHostGetCapabilities

This function gets the capabilities of this Host.

SYNTAX

```
PUBLIC NovaspreadTBoolean
NovaspreadHostGetCapabilities(
   NovaspreadTHostCapabilities * aCapabilities);
```

PARAMETERS

```
aCapabilities
```

OUT: Pointer to a variable of type NovaspreadTHostCapabilities, where the function returns the capabilities.

RETURN VALUE

```
NOVASPREAD_TRUE
if the Host successfully filled all Capabilities members.

NOVASPREAD_FALSE
otherwise
```

3.1.3. NovaspreadHostAllocateTuner

When a SAT>IP client connects to NovaspreadServer, NovaspreadServer calls this function to allocate a tuner for the given TunerAllocationParameter.

When the allocation request is fulfilled, the Tuner must be tuned to the given parameters.

When the Host is able to fulfill the allocation request, the Host shall call the given AllocationFinishedListener and pass the Tuner to NovaspreadServer via this listener.

When the Host denies the allocation request, e.g. because all Tuners are in use by higher priority usages, the Host shall call the AllocationFinishedListener and pass NOVASPREAD_NULL as Tuner via this listener.

NovaspreadHostAllocateTuner() shall not block and return immediately. If the Host can decide during the call of this function whether the request can be fulfilled or must be denied, it may call the AllocationFinishedListener



directly. If it is not possible to process the request while calling this function, this function shall return and the Host shall call the AllocationFinishedListener later.

If no local tuner is available, the Host can create a NovaspreadSatlpTuner by calling NovaspreadServerCreateSatlpTuner() and try to connect it to a SAT>IP LNB by calling NovaspreadSatlpTunerSetParameter() and NovaspreadSatlpTunerConnect(). If the connection is established, this tuner can also be provided via the AllocationFinishedListener.

SYNTAX

```
PUBLIC void

NovaspreadHostAllocateTuner(

NovaspreadTTunerAllocationParameter * aTunerAllocationParameter,

NovaspreadTTunerReleaseRequestedListener aAllocationFinishedListener,

void * aContext):
```

PARAMETERS

aTunerAllocationParameter

A Tuner is requested, which can fulfill this parameter.

```
aAllocationFinishedListener
```

The Host must call this function, when either the allocation request could be fulfilled, or the allocation request is denied.

```
aReleaseRequestedListener
```

NovaspreadServer provides this ReleaseRequestedListener. It can be called by the Host, if a provided tuner is needed for a different usage with a higher priority (e.g. for performing a PVR recording). When this listener is called, NovaspreadServer will call NovaspreadHostReleaseTuner() from within this listener.

```
aContext
```

This context shall be passed to the AllocationFinishedListener and ReleaseRequestedListener when the listener is called.

SEE ALSO

```
NovaspreadTTunerAllocationParameter
NovaspreadTTunerAllocationFinishedListener
NovaspreadTTunerReleaseRequestedListener
```

3.1.4. NovaspreadHostReleaseTuner

This function is called by NovaspreadServer if a tuner is no longer used by NovaspreadServer, e.g. if a SAT>IP client closed the connection.

The Host can use the tuner for another usage. The Host shall not call the ReleaseRequestedListener, which was given during NovaspreadHostAllocateTuner() for this tuner, when NovaspreadHostReleaseTuner() returned.

SYNTAX

```
PUBLIC void
NovaspreadHostReleaseTuner(
NovaspreadTTuner aTuner);
```

PARAMETERS

aTuner

The Tuner which is no longer accessed by NovaspreadServer.

3.2. NovaspreadTuner

The NovaspreadTuner is an interface required by the NovaspreadServer and must be implemented on target platforms to which NovaspreadServer is ported.



The NovaspreadServer allocates a Tuner by calling the NovaspreadHostAllocateTuner() function of the NovaspreadHost. A Tuner is always allocated for a particular transponder. So NovaspreadServer cannot change the tuner parameters (i.e. the transponder) of an already allocated Tuner. Instead NovaspreadServer will release the Tuner and call NovaspreadHostAllocateTuner() for the new tuning parameters.

A Tuner is a combination of a local tuner, transcoder, and transcryptor.

So when a Tuner is allocated, a complete transport stream processing pipeline must be available for this Tuner. See NovaspreadHostAllocateTuner() for details. NovaspreadTunerReadData() can be called to receive transport stream packets from the tuner. Only transport stream packets for pids are received which were set before by calling one of the functions NovaspreadTunerSetPids(), NovaspreadTunerAddPids() or NovaspreadTunerRemovePids(). NovaspreadServer will send these transport stream packets via RTP/UDP to the SAT>IP client.

When a transcoder was requested during NovaspreadHostAllocateTuner(), it shall be possible to change the transcoding parameters of the Tuner at run-time, to allow streaming of a different audio stream. The transcryption parameter can also be changed at run-time.

3.2.1. NovaspreadTTunerError

This type defines various error codes. As long as no error occurred, NovaspreadTunerGetError() shall return NOVASPREAD_TUNER_ERROR_NONE.

SYNTAX

```
typedef enum
{
  NOVASPREAD_TUNER_ERROR_NONE
} NovaspreadTTunerError;
```

COMPONENTS

```
NOVASPREAD_TUNER_ERROR_NONE
No error occurred.
```

3.2.2. NovaspreadTTunerState

This type defines various states of a tuner.

SYNTAX

```
typedef enum
{
    NOVASPREAD_TUNER_STATE_STOPPED,
    NOVASPREAD_TUNER_STATE_STREAMING,
    NOVASPREAD_TUNER_STATE_ERROR
```

} NovaspreadTTunerState;

COMPONENTS

```
NOVASPREAD TUNER STATE STOPPED
```

The tuner is stopped. No data can be read via the tuner's ReadData() function.

```
NOVASPREAD_TUNER_STATE_STREAMING
```

The tuner was started successfully. Data can be read via the tuner's ReadData() function.

```
NOVASPREAD_TUNER_STATE_ERROR
```

An error occurred. When this state is reached, an error code shall be returned when NovaspreadTunerGetError() is called. To leave this state, NovaspreadTunerStop() must be called.

SEE ALSO

NovaspreadTTunerStateChangeListener



3.2.3. NovaspreadTTunerStateChangeListener

A listener of this type can be set at a Tuner. It is called every time the tuner's state changes.

SYNTAX

```
typedef void
(* NovaspreadTTunerStateChangeListener ) (
  void * aContext,
  NovaspreadTTunerState aNewState );
```

PARAMETERS

```
aContext
```

This context is passed unchanged from the NovaspreadTunerSetStateChangeListener() function.

aNewState

The new state of the tuner.

SEE ALSO

NovaspreadTTunerState

3.2.4. NovaspreadTTunerDataAvailableListener

A function of this type can be set at the Tuner. When NovaspreadTunerReadData() returns 0, because no data is available, the registered DataAvailableListener will be called as soon as data is available.

SYNTAX

```
typedef void
(* NovaspreadTTunerDataAvailableListener ) (
  void * aContext );
```

PARAMETERS

aContext

This context is passed unchanged from the NovaspreadTunerSetDataAvailableListener() function.

SEE ALSO

```
NovaspreadTunerSetDataAvailableListener()
NovaspreadTunerReadData()
```

3.2.5. NovaspreadTTunerAllocationParameter

A Tuner is allocated for particular tuner parameters. Additionally it is defined whether a transcoder and a transcryptor are required.

When the allocation request is fulfilled, the Tuner must be tuned to the given tuner parameters.

SYNTAX

```
typedef struct
{
  NovaspreadTTunerParameters TunerParameters;
  NovaspreadTBoolean AllocateTranscoder;
  NovaspreadTBoolean AllocateTranscryptor;
```

} NovaspreadTTunerAllocationParameter;

COMPONENTS

```
TunerParameters
```

A Tuner is requested, which can fulfill this TunerParameter.

```
AllocateTranscoder
```

NOVASPREAD_TRUE if a transcoder shall be allocated. NOVASPREAD_FALSE if no transcoder is required.



AllocateTranscrvptor

NOVASPREAD_TRUE if a transcryptor shall be allocated. NOVASPREAD_FALSE if no transcryptor is required.

SEE ALSO

NovaspreadTTunerParameters

3.2.6. NovaspreadTTunerAllocationFinishedListener

An AllocationFinishedListener is passed to NovaspreadHostAllocateTuner(). The listener shall be called when a Tuner is available, resp. when the allocation request is denied. This callback shall be called only once per allocation request.

SYNTAX

```
typedef void
(* NovaspreadTTunerAllocationFinishedListener )
void * aContext,
NovaspreadTTuner aTuner );
```

PARAMETERS

aContext

The context which was given to NovaspreadHostAllocateTuner() shall be passed unchanged to this listener.

aTuner

A Tuner, if the allocation request could be fulfilled successfully. NOVASPREAD_NULL if the request was denied.

3.2.7. NovaspreadTTunerReleaseRequestedListener

A ReleaseRequestedListener is passed to NovaspreadHostAllocateTuner(). The listener can be called by the Host if the tuner is needed for a usage with higher priority. When this listener is called, the NovaspreadServer will soon call NovaspreadHostReleaseTuner() to release the tuner. This callback shall be called only once per allocation request.

SYNTAX

```
typedef void
(* NovaspreadTTunerReleaseRequestedListener ) (
  void * aContext,
  NovaspreadTTuner aTuner );
```

PARAMETERS

aContext

The context which was given to NovaspreadHostAllocateTuner() shall be passed unchanged to this listener.

aTuner

The Tuner which shall be released.

${\bf 3.2.8.} \quad {\bf Novaspread Tuner Get Transport Session Id}$

Gets the 32-bit TransportSessionId of the Tuner. The returned ID uniquely identifies the stream received by the tuner. This ID is used to indicate the stream to be decrypted with NovaspreadCa functions and for control DRM specific re-encryption with NovaspreadDrm.

SYNTAX

```
PUBLIC NovaspreadTUInt32
NovaspreadTunerGetTransportSessionId(
   NovaspreadTTuner This);
```



PARAMETERS

This
The Tuner.

RETURN VALUE

The 32-bit TransportSessionId.

SEE ALSO

```
NovaspreadTCaServiceUsageRulesReceivedListener NovaspreadCaSetServiceUsageRulesReceivedListener()NovaspreadDrmStart()
```

3.2.9. NovaspreadTunerSetTranscoding

Sets the Transcoding of the Tuner. This function will be called by NovaspreadServer only, if the Tuner was requested for transcoding during NovaspreadHostAllocateTuner().

The transcoding can be changed even if the Tuner is already started. In this case the tuner must check, which part of the transcoding parameters has changed. E.g. if the transcoding parameters for video did not change and only the parameters for audio changed, the video stream shall not be stopped. This is necessary to allow clients to request a different audio stream, e.g. in a different language, without interrupting the video during this change.

SYNTAX

```
PUBLIC NovaspreadTBoolean

NovaspreadTunerSetTranscoding(

NovaspreadTTuner This,

NovaspreadTTranscoding * aTranscoding);
```

PARAMETERS

```
This
The Tuner.

aTranscoding
The Transcoding to be set.
```

RETURN VALUE

```
NOVAS PREAD_TRUE
if the Transcoding was set successfully.

NOVAS PREAD_FALSE
otherwise.
```

SEE ALSO

NovaspreadTTranscoding

${\bf 3.2.10.} \quad {\bf Novaspread Tuner Set State Change Listener}$

Sets a StateChangeListener at this tuner.

SYNTAX

```
PUBLIC NovaspreadTBoolean

NovaspreadTunerSetStateChangeListener(

NovaspreadTTuner This,

NovaspreadTTunerStateChangeListener aListener,

void * aContext);
```

PARAMETERS

This

The tuner.



```
aListener
The listener. Pass NOVASPREAD_NULL to unset the listener.

aContext
This context shall be passed unchanged to the listener.
```

RETURN VALUE

```
NOVAS PREAD_TRUE
if successful

NOVAS PREAD_FALSE
otherwise
```

SEE ALSO

NovaspreadTTunerStateChangeListenerNovaspreadTTunerState

3.2.11. NovaspreadTunerGetError

If the Tuner changed to state ERROR, this function shall return an error code.

SYNTAX

```
PUBLIC NovaspreadTTunerError
NovaspreadTunerGetError(
   NovaspreadTTuner This);
```

PARAMETERS

This

The Tuner.

RETURN VALUE

The error code.

SEE ALSO

NovaspreadTTunerError

3.2.12. NovaspreadTunerSetPids

Sets the pids of the transport stream packets that shall be available in the Tuner's received stream. All previously set pids are replaced by this list. To reset all pids, pass NOVASPREAD_NULL for aPids and set aNoOfPids to 0. This function can be called when the tuner is stopped as well as when the tuner is started.

SYNTAX

```
PUBLIC NovaspreadTBoolean
NovaspreadTunerSetPids (
NovaspreadTuner This,
NovaspreadTUInt16 * aPids,
NovaspreadTUInt32 aNoOfPids );

PARAMETERS

This
The Tuner.

aPids
The array of pids.

aNoOfPids
The number of pids in the array.
```



RETURN VALUE

```
NOVAS PREAD_TRUE
if successful

NOVAS PREAD_FALSE
otherwise
```

3.2.13. NovaspreadTunerAddPids

Adds pids, which shall additionally be received by this Tuner. This function can be called when the tuner is stopped as well as when the Tuner is started.

SYNTAX

```
PUBLIC NovaspreadTBoolean

NovaspreadTunerAddPids (
    NovaspreadTUner This,
    NovaspreadTUInt16 * aPids,
    NovaspreadTUInt32 aNoOfPids );

PARAMETERS

This
    The Tuner.

aPids
    The array of pids that shall additionally be received.

aNoOfPids
    The number of pids in the list.
```

RETURN VALUE

```
NOVAS PREAD_TRUE
if successful

NOVAS PREAD_FALSE
otherwise
```

SEE ALSO

NovaspreadTunerRemovePids()

3.2.14. NovaspreadTunerRemovePids

Removes pids, which should no longer be received by this Tuner. This function can be called when the Tuner is stopped as well as when the tuner is started.

SYNTAX

PUBLIC void

```
NovaspreadTunerRemovePids (
NovaspreadTTuner This,
NovaspreadTUInt16 * aPids,
NovaspreadTUInt32 aNoOfPids );

PARAMETERS

This
The Tuner.

aPids
The array of pids that should no longer be received.

aNoOfPids
The number of pids in the array.
```



SEE ALSO

NovaspreadTunerAddPids()

3.2.15. NovaspreadTunerStart

This function starts the Tuner. When TunerStart() was called, NovaspreadTunerReadData() can be called to receive transport stream data.

Transcryption can be changed only when the tuner is stopped. Pids can be added, removed and set when the tuner is stopped as well as when the tuner is started.

SYNTAX

```
PUBLIC NovaspreadTBoolean
NovaspreadTunerStart(
   NovaspreadTTuner This );
```

PARAMETERS

This

The Tuner.

RETURN VALUE

```
NOVASPREAD_TRUE
if successful

NOVASPREAD_FALSE
otherwise
```

SEE ALSO

NovaspreadTunerStop()

3.2.16. NovaspreadTunerStop

This function stops the data reception of this Tuner.

When this function returns, a registered DataAvailableListener shall no longer be called.

SYNTAX

```
PUBLIC void

NovaspreadTunerStop(

NovaspreadTTuner This);
```

PARAMETERS

This

The Tuner.

SEE ALSO

NovaspreadTunerStart()

3.2.17. NovaspreadTunerIsLocked

Returns whether the Tuner is locked or not. A Tuner is locked if a signal is detected for the set TunerParameter and the demodulator is able to decode the signal. This means a Tuner receives data only if it is locked. A valid lock status is returned if the tuner is started as well as when the tuner is stopped.

SYNTAX

```
PUBLIC NovaspreadTBoolean
NovaspreadTunerIsLocked(
   NovaspreadTTuner This );
```



PARAMETERS

```
This
The Tuner.
```

RETURN VALUE

```
NOVAS PREAD_TRUE
if the Tuner is locked.

NOVAS PREAD_FALSE
otherwise
```

3.2.18. NovaspreadTunerGetSignalInfo

Gets the SignalInfo of this Tuner. See the data type NovaspreadTTunerSignalInfo for a full description of the SignalInfo.

SYNTAX

```
PUBLIC NovaspreadTTunerSignalInfo
NovaspreadTunerGetSignalInfo(
   NovaspreadTTuner This);
```

PARAMETERS

This

The Tuner.

RETURN VALUE

The SignalInfo

SEE ALSO

NovaspreadTTunerSignalInfo

3.2.19. NovaspreadTunerSetDataAvailableListener

Sets a DataAvailableListener. Only one DataAvailableListener can be set at a Tuner.

SYNTAX

```
PUBLIC NovaspreadTBoolean

NovaspreadTunerSetDataAvailableListener(

NovaspreadTTuner

NovaspreadTTunerDataAvailableListener aListener,

void * aContext);

PARAMETERS
```

This

The Tuner.

aListener

 $\label{thm:continuous} The \ Data Available Listener. \ NOVASPREAD_NULL \ is \ passed \ to \ unset \ the \ listener.$

aContext

This context shall be passed unchanged to the listener.

RETURN VALUE

```
NOVAS PREAD_TRUE
if successful

NOVAS PREAD_FALSE
otherwise
```



SEE ALSO

```
NovaspreadTTunerDataAvailableListener NovaspreadTunerReadData()
```

3.2.20. NovaspreadTunerReadData

As soon as the Tuner is started, this function will write 188 bytes long transport stream packets to the buffer. This function must be called periodically to avoid a Tuner internal buffer overflow.

It is not required to write only complete transport stream packets to the buffer. If e.g. a buffer size of 200 bytes is given, and 200 bytes are available, they shall be written to the buffer.

If this function is called when the Tuner is stopped, it will not write data to the buffer and return 0.

If the tuner is started, NovaspreadTunerReadData() will return 0, if no data is available. As soon as data is available again, a previously set DataAvailableListener shall be called.

NovaspreadTunerReadData() will not be called in the context of the DataAvailableListener.

SYNTAX

```
PUBLIC NovaspreadTUInt32
NovaspreadTunerReadData(
NovaspreadTTuner This,
NovaspreadTUInt8 * aBuffer,
NovaspreadTUInt32 aBufferSize);

PARAMETERS
```

This
The Tuner.

aBuffer

Transport stream packets are written to this buffer.

aBufferSize

The size of the buffer.

RETURN VALUE

The number of bytes written to the buffer. If there are no transport stream packets available 0 is returned.

3.3. NovaspreadCa

The NovaspreadCa interface contains functions Novaspread requires from the CA system. The main purpose of this interface is to retrieve the UsageRules on platform and service level from the CA system for a specific stream.

3.3.1. NovaspreadTCaDvbld

The DvbId identifies a DVB service.

SYNTAX

```
typedef struct
{
  NovaspreadTUInt16 OriginalNetworkId;
  NovaspreadTUInt16 TransportStreamId;
  NovaspreadTUInt16 ServiceId;
} NovaspreadTCaDvbId;
```

COMPONENTS

OriginalNetworkId



The OriginalNetworkId

TransportStreamId
The TransportStreamId
ServiceId

The ServiceId

3.3.2. NovaspreadTCaPlatformUsageRulesReceivedListener

This listener must be called, when platform dependent UsageRules have been received. The structure of the passed UsageRules depends on the used CA system.

In case of a Nagra CA system, the payload of the IRD Command defined by tag=0x64 must be passed.

SYNTAX

PARAMETERS

aContext

The context which was given to NovaspreadCaSetPlatformUsageRulesReceivedListener() shall be passed unchanged to this listener.

```
aPlatformUsageRules
```

The UsageRules on platform level.

aLength

The length of the UsageRules buffer.

SEE ALSO

NovaspreadCaSetPlatformUsageRulesReceivedListener()

3.3.3. NovaspreadTCaServiceUsageRulesReceivedListener

A listener of this type can be registered at NovaspreadCa. It is to be called whenever new UsageRules for the particular service are received.

If UsageRules are only received if they are updated, this listener must be called at least once when it is registered with NovaspreadCa.

SYNTAX

PARAMETERS

aContext

This context is passed unchanged from the NovaspreadCaSetUsageRulesReceivedListener() function.

aTransportSessionId

The UsageRules of this TransportSession have been updated.

aServiceUsageRules

The UsageRules on service level. For Nagra these are 3 bytes extracted from the ECM.

aLength

The length of the aServiceUsageRules.



3.3.4. NovaspreadCaGetInfo

This function returns information about the CA system. The returned CaInfo will be destroyed by NovaspreadServer.

SYNTAX

```
PUBLIC NovaspreadTcaInfo
NovaspreadCaGetInfo(
   void );
```

RETURN VALUE

A new Calnfo if successful. NOVASPREAD_NULL otherwise.

SEE ALSO

NovaspreadTCaInfo

EXAMPLE

```
// An implementation of this function shall proceed as follows:
PUBLIC NovaspreadTCaInfo
NovaspreadCaGetInfo ( void )
{
   NovaspradTCaInfo caInfo;
   const char * caVendor = "Nagra";

   caInfo = NovaspreadCaInfoCreate();
   if (! caInfo)
      return NOVASPREAD_NULL;

   // For Nagra, set the NUId by calling
   // NovaspreadCaInfoSetChipsetUid().

   NovaspreadCaInfoSetCaVendor( caInfo, caVendor );

   // Call NovaspreadCaInfoSet..() functions here to set
   // information about the CA system and the smartcard.
   return caInfo;
}
```

3.3.5. NovaspreadCaSetDvbld

Sets the DvbId which is needed for transcryption.

SYNTAX

```
PUBLIC NovaspreadTBoolean
NovaspreadCaSetDvbId(
NovaspreadTUInt32 aTransportSessionId,
NovaspreadTCaDvbId aDvbId);
```

PARAMETERS

```
aTransportSessionId
For this TransportSession the Dvbld is set.

aDvbId
The DvbId to be set.
```



RETURN VALUE

```
NOVAS PREAD_TRUE
if successful

NOVAS PREAD_FALSE
otherwise
```

3.3.6. NovaspreadCaSetPlatformUsageRulesReceivedListener

This functions sets a listener, which shall be called when platform specific usage rules are received.

SYNTAX

```
PUBLIC void
NovaspreadCaSetPlatformUsageRulesReceivedListener(
  NovaspreadTCaPlatformUsageRulesReceivedListener * aListener,
  void * aContext);
```

PARAMETERS

aListener

The PlatformUsageRulesReceivedListener to be set. NOVASPREAD_NULL is passed to unset the listener.

aContext

The context which shall be passed unchanged to the listener.

SEE ALSO

```
NovaspreadTunerGetTransportSessionId()
NovaspreadTCaPlatformUsageRulesReceivedListener
```

3.3.7. NovaspreadCaSetServiceUsageRulesReceivedListener

Sets a ServiceUsageRulesReceivedListener. The TransportSessionId identifies the stream received by a Tuner for which the UsageRules should be acquired. The TransportSessionId can be retrieved with the function NovaspreadTunerGetTransportSessionId().

SYNTAX

```
PUBLIC NovaspreadTBoolean

NovaspreadCaSetServiceUsageRulesReceivedListener(

NovaspreadTUInt32 aTransportSessionId,

NovaspreadTCaServiceUsageRulesReceivedListener aListener,

void * aContext);
```

PARAMETERS

```
aTransportSessionId
```

For this TransportSession the listener is set.

aListener

The ServiceUsageRulesReceivedListener to be set. NOVASPREAD_NULL is passed to unset the listener.

aContext

This context shall be passed unchanged to the listener.

RETURN VALUE

```
NOVAS PREAD_TRUE
if successful

NOVAS PREAD_FALSE
otherwise
```



SEE ALSO

NovaspreadTunerGetTransportSessionId()
NovaspreadTCaServiceUsageRulesReceivedListener

3.4. NovaspreadDrm

The NovaspreadDrm interface contains functions to control the DRM system. With the functions of this interface the encryption of the stream can be controlled. The license for the streamed content can be extracted by the function NovaspreadDrmStart(). This license is passed to Novaspread-C.

3.4.1. NovaspreadTDrmLicense

A license returned by the DRM system.

SYNTAX

```
typedef struct
{
  NovaspreadTUInt8 * License;
  NovaspreadTUInt32 LicenseLength;
} NovaspreadTDrmLicense;
```

COMPONENTS

```
License
```

The License as byte array.

LicenseLength

The length of the License.

3.4.2. NovaspreadTDrmLicenseParameter

This parameter is passed to the NovaspreadDrmStart() function.

If an OldLicense is passed, this license shall be re-used. If this is not possible or if no OldLicense is used, the other components shall be used to create a new license.

SYNTAX

```
typedef struct
{
  NovaspreadTDrmLicense OldLicense;
  NovaspreadTUInt32 Duration;
  NovaspreadTUInt8 * UsageRules;
  NovaspreadTUInt32 UsageRulesLength;
```

} NovaspreadTDrmLicenseParameter;

COMPONENTS

```
OldLicense
```

A license previously returned by a call to NovaspreadDrmStart(). If no OldLicense is available, the content of this OldLicense is 0.

Duration

Defines how long a new license shall be valid. In seconds.

UsageRules

These UsageRules shall be set in TDvlRecordSessionParameters.pSpecifcMetadata.

UsageRulesLength

This UsageRulesLength shall be set in TDvlRecordSessionParameters.specificMetadataSize.



3.4.3. NovaspreadDrmStart

This function starts re-encryption and returns a license.

The TransportSessionId, which is passed to this function, can be got by a call to NovaspreadTunerGetTransportSessionId().

dvlStartRecordEx() shall be called with the given aLicenseParameter and the new license shall be returned.

SYNTAX

PARAMETERS

```
aTransportSessionId
```

For this TransportSession the re-encryption is started.

```
aLicenseParameter
```

The parameters which shall be passed to dvlStartRecordEx()

aLicense

OUT: The new license

RETURN VALUE

```
NOVASPREAD_TRUE
if successful

NOVASPREAD_FALSE
otherwise. In this case there is no need to call NovaspreadDrmStop().
```

SEE ALSO

```
NovaspreadTunerGetTransportSessionId()
NovaspreadDrmStop()
NovaspreadTDrmLicenseParameter
NovaspreadTDrmLicense
```

3.4.4. NovaspreadDrmStop

Stops the re-encryption of the stream.

For Nagra dvlStopRecord() shall be called.

SYNTAX

```
PUBLIC void
NovaspreadDrmStop(
   NovaspreadTUInt32 aTransportSessionId );
```

PARAMETERS

```
aTransportSessionId
```

For this TransportSession the encryption is stopped.

SEE ALSO

```
NovaspreadDrmStart
NovaspreadTunerGetTransportSessionId()
```

Published by:

SES Platform Services GmbH

Beta Straße 1-10 85774 Unterföhring Germany

For more information about SES, visit www.ses-ps.com or email info@ses-ps.com

The information and data contained herein are subject to change.